

## **NEW LOCATIONS FOR LICENSE AND CONFIGURATION FILES AFTER v7.3.623.51 dated 6/21/2010**

**License Files – must** still be placed in:

C:\Program Files\Triton Imaging, Inc\License Files

Under all operating systems, assuming the user installs to the default location.

### **The LicenseDump.txt file:**

Windows XP > C:\Documents and Settings\<<UserName>\Application Data\Triton Imaging, Inc\License Files

Windows 7 \ Vista > C:\Program Data\Triton Imaging, Inc\License Files

### **.CFG files for Isis and Sonar Servers:**

Windows XP > C:\Documents and Settings\<<User Name>\Local Settings\Application Data\Triton Imaging, Inc\<<app name>\

Windows 7\ Vista > C:\Users\<<user name>\App Data\Local\Triton Imagin, Inc\<<app name>\

Example: for user “Geoff” and the application “Isis” the Isis configuration file under Windows 7 would be in:

C:\Users\Geoff\AppData\Local\Triton Imaging, Inc\Isis\

### **BathyPro.INI file:**

Windows XP > C:\Documents and Settings\All Users\Shared Documents\Triton Imaging, Inc\bathypro

Windows 7\ Vista > C:\Users\Public\Public Documents\Triton Imaging, Inc\bathypro

### **TritonMap.INI file:**

Windows XP > C:\Documents and Settings\<<user name>\Local Settings\Application Data\Triton Imaging, Inc\TritonMap\

Windows 7\ Vista > C:\Users\<<user name>\AppData\Local\Triton Imaging, Inc\TritonMap\

### **TargetPro.INI file:**

Windows XP > C:\Documents and Settings\<<user name>\Local Settings\Application Data\Triton Imaging, Inc\TargetPro

Windows 7\ Vista > C:\Users\<<user name>\AppData\Local\Triton Imaging, Inc\TargetPro\

### **TritonSerial.INI**

Windows XP > C:\Windows

Windows 7 \ Vista > C:\Winbows

### **TritonEmServer.INI**

Windows XP > C:\Windows

Windows 7 \ Vista > C:\Windows

### **HydroNavInfos.INI**

Windows XP > C:\Windows

Windows 7 \ Vista > C:\Windows

### **ProjWizard.INI**

Windows XP > C:\Windows

Windows7 \ Vista > C:\Windows